

PS Financials Powering Better Business Decisions

PSF Document Scanning

Printer Setup(DYMO LabelWriter 450)

Install the drivers for the **DYMO LabelWriter 450**. In the Installation directory there is a file called "**DLS8Setup.8.5.1.exe**". Double click this to install the drivers.

Run through the installation steps, when you get to the following screen, click "Custom Installation".



You will then get a couple of options of what you would like to install. Un-tick "**DYMO Label**", then click "**Next**" to carry on with the installation.

6	DYMO Label Setup	- 🗆 🗙		
Choose Components Choose which features of DYMO Label v.8 you want to install.				
Check the components you want to install and uncheck the components you don't want to install. Click Next to continue.				
Select components to install:	Printer Drivers DYMO Labe	Description Position your mouse over a component to see its description.		
Space required: 51.30 MB				
	< <u>B</u> ack	Next > Cancel		

Right Click the "DYMO LabelWriter 450", select "Printer Properties"



Click the "Advanced" tab and then select "Printing Defaults"



On the "Layout" tab, check the settings are the same as the below screenshot.

🖶 DYMO LabelWriter 450 Printing Defaults		
Layout Paper/Quality		
Orientation:		
A Portrait V		
Page Order:		
Front to Back 🗸 🗸		
Page Format	-	
Pages per Sheet 1 🗸		
Draw Borders		
	=-	
	Advanced	
	OK Cancel Apply	

Then click on "Paper/Quality"

Click the "Custom" box and then click "Advanced".

🖶 DYMO LabelWriter 450 Printing Defaults 🛛 🗙				
Layout Paper/Quality				_
Quality Settings				
🔘 Be	st	Normal	Custom	
			Advanced	
		ОК	Cancel Apply	

Check that all of the settings match the below screenshot.



You may see a ^(A) next to some of the options; this is because the printer will need to change some of the other configuration parts to make it work correctly. This will usually come up with you select "**Barcode and Graphics**" from the "**Print Quality:**" option.

Select "OK"

🖶 DYMO LabelWriter 450 Printing Defaults 🛛 🗙					
Layout Paper/Quality					
Quality Settings					
<u>B</u> est	Normal	✓ C <u>u</u> stom			
		Ad <u>v</u> anced			
	ок	Cancel Apply			

Then on the following window, click "**Apply**". You should then receive the following message:



Click "OK" to that message, and then "OK" to close the configuration screen.

Check that the above settings are the same under the "**Printing preferences**" option menu when you right click the **DYMO LabelWriter 450**. If they are not the same, alter these to match the above settings.

